

**Kurze Installationsanleitung von wc3270
auf Windows XP
für den Zugriff auf hobbit.cs.uni-tuebingen.de
(134.2.205.54)**

Beim Starten von wc3270-3.3.8b1-setup.exe erscheint ein "wc3270 Setup Wizard", bei dem man im Normalfall immer "Next" drueckt und zuletzt mit "Install" and "Finish" die Installation abschliesst.

Anschliessend erscheint der "wc3270 Session Wizard", um Session's anzulegen, die dann im Desktop abgelegt werden.
Fuer den Zugriff auf hobbit sind folgende Werte einzustellen:

**Zugriff mit SSL-Verschluesselung (empfohlen) auf dem
Standartport 23 (telnet):**

wc3270 Session Wizard

v3.3.8b1

Session: hobbit-ssl

```
Host: 134.2.205.54
TCP Port: 23
Model Number: 4 (43 rows x 80 columns)
Character Set: bracket
SSL Tunnel: Yes
Proxy: No
wpr3287 Printer Session: No
Keymaps: none
```

Create the session? (y/n) [y]

Zugriff ohne SSL-Verschlüsselung auf dem Port 423:

wc3270 Session Wizard

v3.3.8b1

Session: hobbit-insecure

Host: 134.2.205.54
TCP Port: 423
Model Number: 4 (43 rows x 80 columns)
Character Set: bracket
SSL Tunnel: No
Proxy: No
wpr3287 Printer Session: No
Keymaps: none

Create the session? (y/n) [y]

```
C:\Programme\wc3270\wc3270wiz.exe
wc3270 Session Wizard v3.3.8b1
Session Name
This is a unique name for the wc3270 session. It is the name of the file
containing the session configuration parameters and the name of the desktop
shortcut.
Enter session name: Hobbit
```

```
C:\Programme\wc3270\wc3270wiz.exe
wc3270 Session Wizard v3.3.8b1
Session: Hobbit
Host Name
This specifies the IBM host to connect to. It can be a symbolic name like
'foo.company.com', an IPv4 address in dotted-decimal notation such as
'1.2.3.4' or an IPv6 address in colon notation, such as 'fec0:0:0:1::27'.
Enter host name or IP address: [Hobbit] 134.2.205.54
```

```
C:\Programme\wc3270\wc3270wiz.exe
wc3270 Session Wizard v3.3.8b1
Session: Hobbit
TCP Port
This specifies the TCP Port to use to connect to the host. It is a number from
1 to 65535 or the name 'telnet'. The default is the 'telnet' port, port 23.
TCP port: [telnet] 423
```

```
C:\Programme\wc3270\wc3270wiz.exe
wc3270 Session Wizard v3.3.8b1
Session: Hobbit
Logical Unit <LU> Name
This specifies a particular Logical Unit or Logical Unit group to connect to
on the host. The default is to allow the host to select the Logical Unit.
Enter Logical Unit <LU> name: [none] _
```

```
C:\Programme\wc3270\wc3270wiz.exe
wc3270 Session Wizard v3.3.8b1
Session: Hobbit
Model Number
This specifies the dimensions of the screen.
Model 2 has 24 rows and 80 columns.
Model 3 has 32 rows and 80 columns.
Model 4 has 43 rows and 80 columns.
Model 5 has 27 rows and 132 columns.
Enter model number: <2, 3, 4 or 5> [4] 2
```

```
C:\Programme\wc3270\wc3270wiz.exe
wc3270 Session Wizard v3.3.8b1
Session: Hobbit
Character Set
This specifies the EBCDIC character set used by the host.
Available character sets:
Name Host CP Name Host CP
-----
1. belgian 500 16. icelandic 871
2. belgian-euro 1148 17. icelandic-euro 1149
3. bracket 37+ 18. italian 280
4. brazilian 275 19. italian-euro 1144
5. cp1047 1047 20. norwegian 277
6. cp1153 1153 21. norwegian-euro 1142
7. cp870 870 22. russian 880
8. finnish 278 23. spanish 284
9. finnish-euro 1143 24. spanish-euro 1145
10. french 297 25. thai 838
11. french-euro 1147 26. turkish 1026
12. german 273 27. uk 285
13. german-euro 1141 28. uk-euro 1146
14. greek 875 29. us-euro 1140
15. hebrew 424 30. us-intl 37
Character set: [bracket] 29
```

```
C:\Programme\wc3270\wc3270wiz.exe
wc3270 Session Wizard v3.3.8b1
Session: Hobbit
SSL Tunnel
This option causes wc3270 to first create a tunnel to the host using the
Secure Sockets Layer (SSL), then to run the TN3270 session inside the tunnel.
Use an SSL tunnel? <y/n> [n] n_
```

```
C:\Programme\wc3270\wc3270wiz.exe
wc3270 Session Wizard v3.3.8b1
Session: Hobbit
Proxy
If you do not have a direct connection to your host, this option allows
wc3270 to use a proxy server to make the connection.
Proxy types available:
none Direct connection to host
http HTTP tunnel (RFC 2817, e.g., squid)
passthru Sun telnet-passthru
socks4 SOCKS version 4
socks5 SOCKS version 5 (RFC 1928)
telnet None (just send 'connect host port')
Proxy type: [none] _
```

```
C:\Programme\wc3270\wc3270wiz.exe
wc3270 Session Wizard v3.3.8b1
Session: Hobbit
wpr3287 Session
This option allows wc3270 to automatically start a wpr3287 printer session
when it connects to the host, allowing the host to direct print jobs to a
Windows printer.
Automatically start a wpr3287 printer session? (y/n) [n] _
```

```
C:\Programme\wc3270\wc3270wiz.exe
wc3270 Session Wizard v3.3.8b1
Session: Hobbit
Keymaps
A keymap is a mapping from the PC keyboard to the virtual 3270 keyboard.
You can override the default keymap and specify one or more built-in or
user-defined keymaps, separated by commas.
    rctrl
    Map PC Right Ctrl key to 3270 'Enter' and PC Enter key to 3270 'Newline'
Enter keymap name(s) [none]:
```

```
C:\Programme\wc3270\wc3270wiz.exe
wc3270 Session Wizard v3.3.8b1
Session: Hobbit
Host: 134.2.205.54
TCP Port: 423
Model Number: 2 (24 rows x 80 columns)
Character Set: us-euro
SSL Tunnel: No
Proxy: No
wpr3287 Printer Session: No
Keymaps: none
Create the session? (y/n) [y] y
```

```
C:\Programme\wc3270\wc3270wiz.exe
wc3270 Session Wizard v3.3.8b1
Session: Hobbit
Host: 134.2.205.54
TCP Port: 423
Model Number: 2 (24 rows x 80 columns)
Character Set: us-euro
SSL Tunnel: No
Proxy: No
wpr3287 Printer Session: No
Keymaps: none
Create the session? (y/n) [y] y
Creating session file 'C:\Dokumente und Einstellungen\Spruth\Anwendungsdaten\wc3
270\Hobbit.wc3270' ... done
Create desktop shortcut (y/n) [y]: y
```